Version I.0

Adapted from the tool "Estimation of carbon stocks and change in carbon stocks of trees and shrubs in A/R CDM project activities" version 04.1, UNFCCC.



September 2012



Version I.0 – Scope 17

I. INTRODUCTION

I. This tool provides step-by-step methods for estimation of carbon stock in living biomass of trees and shrubs. For ex-ante (projected) estimation of tree biomass it applies tree growth and stand development models. For ex-post (actual) estimation of tree biomass it uses data from measurements conducted in sample plots. Remote sensing data may also be used in conjunction with data from measurements conducted in sample plots. Biomass of shrubs is estimated from shrub crown cover

SCOPE, APPLICABILITY AND ENTRY INTO FORCE

Scope

- 2. This tool can be used for estimations of carbon stocks and change in carbon stocks in the living biomass in trees and shrubs related to ZERO2NATURETM-PREFOR project activities. This tool is applicable in the following cases:
 - (a) Estimations of carbon stocks and change in carbon stocks of living biomass in the baseline trees and shrubs;
 - (b) Ex ante estimations of carbon stocks and change in carbon stocks in living biomass of trees and shrubs related to ZERO2NATURETM-PREFOR project activities;
 - (c) Ex post estimations of carbon stocks and change in carbon stocks in living biomass of trees and shrubs related to the monitoring system of the ZERO2NATURETM-PREFOR project activity.

Applicability

3. This tool has no internal applicability conditions.

Entry into force

4. The date into force of this tool is September 20, 2012.

3. DEFINITIONS AND NOTATIONS

- 5. The definitions contained in the Glossary of ZERO2NATURETM terms shall apply.
- 6. For the purpose of this tool, the following definitions apply:
- (a) Species can also refer to a species group when a species-specific biometric parameter (e.g. biomass expansion factor), or a model (e.g. allometric equation), is demonstrated to be applicable



Version I.0 – Scope 17

to more than one species;

- (b) Tree biomass refers to above-ground and below-ground living biomass of trees;
- (c) Shrub biomass refers to above-ground and below-ground living biomass of shrubs;
- (d) Plot biomass refers to tree biomass per hectare in a plot;
- (e) Measurement of a sample plot refers to the measurement of one or more dimensions (e.g. diameter) of the trees in a sample plot, or measurement of a plot parameter (e.g. basal area per hectare), and conversion of the measured tree dimensions, or the measured plot parameter into plot biomass by using one of the methods provided in appendix I;
- (f) Conservative value of a parameter refers to the value which, when used in calculations, is more likely to result in underestimation rather than overestimation of the net anthropic negative emissions removals by sinks;
- 7. This tool uses the following units in their abbreviated form:
- (a) Tonne dry matter is abbreviated as t d.m., and tonne dry matter per hectare is abbreviated as t d.m. ha⁻¹;
- (b) Tonne carbon dioxide equivalent is abbreviated as t CO2e;
- (c) O Environmental Impact Potential EIP of each negative emitter will be measured in tonnes or briefly em tEIP.

4. PARAMETERS DETERMINED BY THE TOOL

8. This tool provides procedures to determine the parameters listed in table 1.

Table I. Parameters determined by the tool

Parameter	Unit	Description
		Carbon stock in tree biomass within the project boundary at a given point of
Ctree,y	tEIP	time in year <i>y</i>
$\Delta C_{ ext{tree,y}}$	tEIP	Change in carbon stock in tree biomass within the project boundary in year y
		Carbon stock in shrub biomass within the project boundary at a given point of
Cshrub,y	tEIP	time in year <i>y</i>
ΔCshrub,y	tEIP	Change in carbon stock in shrub biomass within the project boundary in year y



Version I.0 – Scope 17

- 9. While applying this tool in an approved ZERO2NATURETM methodology, the following corresponding notations should be used:
- (a) In the baseline scenario:

Ctree_bsl,y for Ctree,y and Cshrub_bsl,y for Cshrub,y

 Δ Ctree_bsl,y for Δ Ctree,y and Δ Cshrub_bsl,y for Δ Cshrub,y

(b) in the project scenario:

CTREE_PROJ,y for CTREE,y and CSHRUB_PROJ,y for CSHRUB,y

 $\Delta C_{TREE_PROJ,ty} for \Delta C_{TREE,y} and \Delta C_{SHRUB_PROJ,y} for \Delta C_{SHRUB,y}$

5. CONDITIONS UNDER WHICH CARBON STOCK AND CHANGE IN CARBON STOCK MAY BE ESTIMATED AS ZERO

- 10. Carbon stock in trees in the baseline can be accounted as zero if all of the following conditions are met:
- (a) The pre-project trees are neither harvested, nor cleared, nor removed throughout the crediting period of the project activity;
- (b) The pre-project trees do not suffer mortality because of competition from trees planted in the project, or damage because of implementation of the project activity, at any time during the crediting period of the project activity;
- II. Related to ZERO2NATURE™-PREFOR monitored preservation project activity, changes in carbon stocks in trees and shrubs in the baseline will be accounted as zero.
- 12. For the purpose of ex-ante estimation of carbon stock and change in carbon stock in the project scenario, change in carbon stock of shrubs may be estimated as zero.

6. ESTIMATING CHANGE IN CARBON STOCK IN TREES BETWEEN THE FIRST YEAR OF THE PROJECT AND THE SUBSEQUENT YEARS

- 13. Change in carbon stock in trees between the first year of the project and the subsequent is estimated using one of the two methods:
- (a) by using direct estimation of change by re-measurement of sample plots. Under this method, the same sample plots are measured on two successive occasions and the plot-level change in biomass is obtained by subtracting the plot biomass on the first occasion from the plot biomass



Version I.0 – Scope 17

on the second occasion;

(b) Taking in consideration the forest depletion rate which can be proved through objective evidences like official data, renowned entities studies or through criteria of proportionality, considering deforestation official data related to the project activity area and applying annual deforestation average arithmetic from 20% deforestation of the original forest until the beginning of the ZERO2NATURETM-PREFOR; always adopting the most conservative possible scenario.

6.1. Demonstration of "no-decrease"

- 14. This method is applicable only in ex-post estimation of change in carbon stock in trees for monitoring of project activities. Project participants may, at the time of a verification, demonstrate that tree biomass in one or more strata has not decreased relative to the tree biomass at the time of the previous verification, by proving that:
- (a) No harvest has occurred in the stratum since the previous verification;
- (b) The stratum was not affected by any disturbance (e.g. pest, fire) that would decrease the carbon stock in trees;
- (c) Remote sensing data or inventory data, including participatory inventory or participatory photo-mapping data, demonstrate that tree crown cover in the stratum has not decreased since the previous verification.

6.2. Amazonian living biomass carbon quantity

According to studies published by the National Institute of Amazonian Research (INPA, in Portuguese) and adopted by the ZERO2NATURETM Standard, the average Amazonian living biomass (dry weight above and below the soil) is estimated in 247 tonnes per hectare and the carbon quantity represents 50%.

	Document information	
Version	Date	Description
1.0	September 24, 2012	Tool