

Version I.0

Developed from the UNFCCC methodological concept."



September 2012



Version I.0 – Scope 17

I. INTRODUCTION

This tool provides a step-by-step method for estimating carbon stocks and change in carbon stocks in dead wood and/or waste in the baseline and project scenarios of a ZERO2NATURETM-PREFOR project activity. The tool provides methods based on field measurements. Simplified methods based on conservative default factors are also available where certain conditions are met.

2. SCOPE, APPLICABILITY, AND ENTRY INTO FORCE

2.I. Scope

This tool can be used for estimation of carbon stocks and change in carbon stocks in dead wood and/or waste in the baseline and project scenarios of A ZERO2NATURE™-PREFOR project activity.

2.2. Applicability

This tool has no internal applicability conditions.

This tool makes the following assumptions:

(a) Linearity of change of biomass in dead wood and waste over a period of time:

Change of biomass in dead wood and waste may be assumed to proceed, on average, at an approximately constant rate between two points of time at which the biomass is estimated;

(b) Appropriateness of root-shoot ratios:

Root-shoot ratios appropriate for estimation of below-ground biomass from above-ground biomass of living trees are also appropriate for dead trees.

2.3. Entry into force

The date of entry into force of this tool is September 24, 2012.

3. NORMATIVE REFERENCES

The following documents are indispensable for the application of this tool:

- (a) Glossary of ZERO2NATURE™ terms;
- (b) Tool "Estimation of carbon stocks and change in carbon stocks of trees and shrubs in ZERO2NATURE™-PREFOR project activities";
- (c) ZERO2NATURETM standard.

4. DEFINITIONS

The definitions contained in the Glossary of ZERO2NATURE™ terms shall apply. Where a



Version I.0 – Scope 17

term is not defined in the Glossary of ZERO2NATURETM terms, project participants should consult the definitions provided in the *IPCC Good Practice Guidance for Land Use, Land-Use Change and Forestry* (IPCC GPG-LULUCF 2003).

5. PARAMETERS

This tool provides procedures to determine the following parameters:

Table 1. Parameters determined by the tool

Parameter	Unit	Description
$C_{DW,y}$	tEIP	Carbon stock in dead wood within the project boundary at a given point of time in year y
$\Delta C_{DW,y}$	tEIP	Change in carbon stock in dead wood within the project boundary in year y
$C_{LI,y}$	tEIP	Carbon stock in waste within the project boundary at a given point of time in year y
$\Delta C_{LI,y}$	tEIP	Change in carbon stock in wastewithin the project boundary in year <i>y</i>

While applying this tool in a methodology, the following notation should be used:

(a) In the baseline scenario:

 $C_{DW_BSL,y}$ for $C_{DW,y}$ and $C_{W_BSL,y}$ for $C_{W',y}$;

 $\Delta C_{DW_BSL,y}$ for $\Delta C_{DW,y}$ and $\Delta C_{W_BSL,y}$ for $\Delta C_{W,y}$

(b) In the project scenario:

 $C_{DW\ PROJ,y}$ for $C_{DW,y}$ and $C_{W\ PROJ,y}$ for $C_{W,y}$;

 $\Delta C_{DW_PROJ,y}$ for $\Delta C_{DW,y}$ and $\Delta C_{W_PROJ,y}$ for $\Delta C_{W,y}$

6. ESTIMATION OF CARBON STOCK AND CHANGE IN CARBON STOCK IN DEAD WOOD

Carbon stock in dead wood is estimated on the basis of the same strata, and the same sample plots, which are used for the purpose of estimation of living tree biomass. However, project participants (PPs) applying this tool may use a different stratification for the purpose of estimation of carbon stock in dead wood if transparent and verifiable information can be given for justification of such a choice.

Two methods are offered for estimation of carbon stock in dead wood: a measurement-based method and a conservative default-factor based method.



Version 1.0 – Scope 17

6.I. Measurement-based methods for estimation of carbon stock in dead wood

For the purpose of this tool, the term "species" also implies a group of species when a biometric parameter (e.g. biomass expansion factor, root-shoot ratio, basic wood density) or a model (e.g. allometric equation, volume equation or table) is applicable to more than one species.

Biomass of dead wood of species j in sample plot p in stratum i at a given point of time in year y is calculated separately for the following two types of dead wood:

- (a) Standing dead wood;
- (b) Lying dead wood.

Note: Uprooted trees lying on the ground, if not extracted, shall be treated as "standing dead wood" for estimation of deadwood biomass.

6.I.I. Standing dead wood

For the following two categories of standing dead wood, the biomass of standing dead wood is estimated by applying a biomass reduction factor to whole tree biomass:

(a) Dead trees which have lost only leaves and twigs.

Dead wood biomass is equal to whole tree biomass multiplied by a biomass reduction factor equal to 0.975:

(b) Dead trees which have lost leaves, twigs and small branches (diameter < 10 cm).

Dead wood biomass is equal to whole tree biomass multiplied by a biomass reduction factor equal to 0.80.

6.I.I.I. Estimation of standing dead tree biomass using BEF method

Under this method volume tables (or volume functions/curves) are used to convert tree dimensions to stem volume of trees. Stem volume of trees is converted to above-ground tree biomass using basic wood density and biomass expansion factors and the above-ground tree biomass is expanded to total tree biomass using root-shoot ratios. Thus, dead wood biomass in standing dead trees of species *f* in sample plot *p* is calculated as:



Version I.0 – Scope 17

$B_{DWS_TREE,j,p,i,y} = I$	$D_j \times$	$BEF_{2,j} \times (1+R_j) \times \sum_{k=1}^{K} V_{TREE,j} \left(DBH_{k,}H_{k}\right) \times \alpha_{k}$ Equation (1)
Where:		
$B_{DWS_TREE,j,p,i,y}$	=	Biomass of dead wood in dead trees of species j in sample plot p of stratum i at a point of time in year y ; t d.m.
$V_{\mathit{TREE},j}(\mathit{DBH}_k,\!H_k)$	=	Stem volume of the k^{th} dead tree of species j in plot p of stratum i as returned by the volume function for species j using the tree dimension(s) as entry data; m^3
DBH_k	=	Diameter of the k^{th} dead tree of species j in plot p of stratum i at a point of time in year y ; metre or any other unit of length used by the volume function
H_k	=	Height of the k^{th} dead tree of species j in plot p of stratum i at a point of time in year y ; metre or any other unit of length used by the volume function
α_k	=	Biomass reduction factor for the k^{th} dead tree, depending upon its category; dimensionless
D_j	=	Basic wood density of species j; t d.m. m ⁻³
$BEF_{2,j}$	=	Biomass expansion factor for conversion of stem biomass to above-ground tree biomass, for species <i>j</i> ; dimensionless
R_j	=	Root-shoot ratio for tree species j; dimensionless
j	=	1, 2, 3, tree species in plot p
k	=	1, 2, 3, dead trees of species j in plot p in stratum i
p	=	1, 2, 3, sample plots in stratum i
i	=	1, 2, 3, biomass estimation strata within the project boundary
у	=	1, 2, 3, years elapsed since the start of the <code>zero2NATURE-PREFOR</code> project activity

6.1.1.2. Estimation of standing dead tree biomass using allometric method

Under this method allometric equations are used to convert tree dimensions to above-ground biomass of trees and the above-ground tree biomass is expanded to total tree biomass using root-shoot ratios. Thus, dead wood biomass in standing dead trees of species j in sample plot p is calculated as:



Version I.0 – Scope 17

$$B_{DWS_TREE,j,p,i,y} = (1+R_j) \times \sum_{k=1}^{K} f_j \left(DBH_k,H_k\right) \times \alpha_k$$
 Equation (2)

Where:

where.		
$B_{DWS_TREE,j,p,i,y}$		ass of dead wood in standing dead trees of species j in le plot p of stratum i at a point of time in year y ; t d.m.
$f_j(DBH_k,H_k)$	plot p	e-ground biomass of the k^{th} dead tree of species j in sample of stratum i returned by the allometric function for species j the tree dimension(s) as entry data; t d.m.
α_k		ass reduction factor for the k^{th} dead tree, depending upon its tion; dimensionless
R_j	= Root-	shoot ratio for tree species j; dimensionless
j	= 1, 2, 3	B, \dots tree species in plot p
\boldsymbol{k}	= 1, 2, 3	β , dead trees of species j in plot p in stratum i
p	= 1, 2, 3	3, sample plots in stratum <i>i</i>
i	= 1, 2, 3	3, biomass estimation strata within the project boundary
У	= 1, 2, 3	8, years elapsed since the start of the ZERO2NATURE-PREFOR

6.I.I.3. Estimation of carbon stock in standing dead wood in dead trees

project activity

In both the *BEF* method and the allometric method, the carbon stock in dead wood biomass in standing dead trees of species *j* in sample plot *p* of stratum *i* is calculated as follows:



Version I.0 – Scope 17

$$C_{DWS_TREE,j,p,i,y} = \frac{44}{12} \times CF_{TREE} \times B_{DWS_TREE,j,p,i,y}$$
 Equation (3)

Where:

 $C_{DWS_TREE,j,p,i,y}$ = Carbon stock in dead wood in standing dead trees of species j in sample plot p in stratum i at a given point of time in year y; t CO₂e

 CF_{TREE} = Carbon fraction of tree biomass; dimensionless

 $B_{DWS_TREE,j,p,i,y}$ = Biomass of dead wood in standing dead trees of species j in sample plot p of stratum i at a point of time in yeary; t d.m.

 $j = 1, 2, 3, \dots$ tree species in plot p

 $p = 1, 2, 3, \dots$ sample plots in stratum i

i = 1, 2, 3, ... biomass estimation strata within the project boundary

y = 1, 2, 3, ... years elapsed since the start of the ZERO2NATURE-PREFOR project activity

6.I.I.4. Estimation of carbon stock in standing dead wood in tree stumps

Each dead tree stump in a sample plot is categorized into a decay class as:

- (a) Sound;
- (b) Intermediate; or
- (c) Rotten.

A density reduction factor is assigned to each of the decay classes, which is to be multiplied by the basic wood density of the species of the stump to obtain its estimated wood density. The following default values of the density reduction factors for the three decay classes are used, unless PPs have more specific data available with them: for the decay class: (a) Sound, the density reduction factor = 1.00; for the decay class; (b) Intermediate, the density reduction factor = 0.80; for the decay class; and (c) Rotten, the density reduction factor = 0.45.

For each dead tree stump of height less than 4m the mid-height diameter is measured. For each dead tree stump of height 4m and above, the diameter at breast height (*DBH*) is measured.

For stumps of height more than 4 m, the mid-height diameter of the stump is estimated as:



Version I.0 – Scope 17

$$D_{MID_STUMP} = 0.57 \times DBH \times \left(\frac{H_{STUMP}}{H_{STUMP} - H_{DBH}}\right)^{0.80} \text{ for } H_{STUMP} > 4 \text{ m}$$
 Equation (4)

Where:

 $D_{MID\ STUMP}$ = Mid-height diameter of the dead tree stump; m

DBH = Diameter at breast height of the dead tree stump; m

 H_{STUMP} = Height of the stump; m

 H_{DBH} = Height above ground level at which DBH is measured; m

Carbon stock in dead wood in dead tree stumps of species j in plot p is calculated as:

$$C_{DWS_STUMP,j,p,i,y} = \frac{44}{12} \times CF_{TREE} \times D_j \times \left(1 + R_j\right) \times \frac{\pi}{4} \sum_k D_{MID_STUMP,k}^2 \times \qquad \qquad \text{Equation (5)}$$

 $H_k * \beta_k$

Where:

 $C_{DWS_STUMP,j,p,i,y}$ = Carbon stock in dead wood in dead tree stumps of species j in

sample plot p in stratum i at a given point of time in year y; t EIP

 CF_{TREE} = Carbon fraction of tree biomass; dimensionless

 D_i = Basic wood density of species j; t d.m. m⁻³

 R_i = Root-shoot ratio for tree species j; dimensionless

 $D_{MID\ STUMP,k}$ = Mid-height diameter of the k^{th} dead tree stump of species j in

plot p in stratum i at a given point of time in yeary; m

 H_k = Height of the k^{th} dead tree stump of species j in plot p in stratum i

at a given point of time in yeary; m

 β_k = Density reduction factor applicable to the k^{th} dead tree stump of

species *j* in plot *p* in stratum *i* at a given point of time in year *y*;

dimensionless

j = 1, 2, 3, ... tree species in plot p

k = 1, 2, 3, ... dead trees of species j in plot p in stratum i

 $p = 1, 2, 3, \dots$ sample plots in stratum i

i = 1, 2, 3, ... biomass estimation strata within the project boundary

y = 1, 2, 3, ... years elapsed since the start of the ZERO2NATURE-PREFOR

project activity



Version I.0 – Scope 17

6.I.2. Lying dead wood

Lying dead wood is estimated by using line transect method (Harmon and Sexton, 1996). Two transect lines, of total length of at least 100 m, approximately orthogonally bisecting each other at the centre of the plot are established and the diameter of each piece of lying dead wood (with diameter \geq 10 cm) intersecting a transect line is measured.

Each piece of dead wood is assigned to one of three decay classes and each of the three decay classes are assigned a density reduction factor as explained.

Based on these measurements and categorization into decay classes, carbon stock in lying dead wood of species *j* in plot *p* is calculated as:

$$C_{DWL,j,p,i,y} = \frac{44}{12} \times CF_{TREE} \times D_j * \frac{\pi^2}{8L} \times \sum_{n=1}^{N} D_{n^2} * \beta_n$$
 Equation (6)

Where:

$C_{DWL,j,p,i,y}$	=	Carbon stock in lying dead wood of species j in sample plot p in stratum i at a given point of time in year y ; t EIP
CF_{TREE}	=	Carbon fraction of tree biomass; dimensionless
D_j	=	Basic wood density of species j; t d.m. m ⁻³
L	=	Sum of the lengths of the transect lines approximately orthogonally bisecting each other at the centre of the plot p ; m
D_n	=	Diameter of the n^{th} piece of lying dead wood intersecting a transect line; cm
β_n	=	Density reduction factor applicable to the n^{th} piece of lying dead wood intersecting a transect line; dimensionless
j	=	1, 2, 3, tree species in plot p
p	=	1, 2, 3, sample plots in stratum i
i	=	1, 2, 3, biomass estimation strata within the project boundary
у	=	1, 2, 3, \dots years elapsed since the start of the <code>zero2NATURE-PREFOR</code> project activity

The carbon stock in dead wood in a stratum is then calculated as:



Version I.0 – Scope 17

$$C_{DW,i,y} = \frac{A_i}{A_{PLOT,i}} \sum_{p} \sum_{j} \left(C_{DWS_TREE,j,p,i,y} + C_{DWS_STUMP,j,p,i,y} + C_{DWS_STUMP,j,p,i,y} \right)$$

$$+ C_{DWL,i,p,i,y} \right)$$
Equation (7)

Where:

 $C_{DW,i,y}$ = Carbon stock in dead wood in stratum i at a given point of time in

yeary; t EIP

 A_i = Total area of stratum i; ha

 $A_{PLOT.i}$ = Total area of sample plots in stratum i; ha

 $C_{DWS_TREE,j,p,i,y}$ = Carbon stock in dead wood in standing dead trees of species j in

sample plot p in stratum i at a given point of time in year y; $t \in P$

 $C_{DWS_STUMP,j,p,i,y}$ = Carbon stock in dead wood in dead tree stumps of species j in

sample plot p in stratum i at a given point of time in year y; t EIP

 $C_{DWL,j,p,i,y}$ = Carbon stock in lying dead wood of species j in sample plot p in

stratum i at a given point of time in yeary; t EIP

i = 1, 2, 3, ... tree species in plot p

 $p = 1, 2, 3, \dots$ sample plots in stratum i

i = 1, 2, 3, ... biomass estimation strata within the project boundary

y = 1, 2, 3, ... years elapsed since the start of the ZERO2NATURE-PREFOR project activity

Finally, the carbon stock in dead tree biomass within the project boundary at a given point of time in year *y* is calculated by summing up over all the strata, that is:



Version I.0 – Scope I7

$C_{DW,y} = \sum_{i} C_{DW}$	7,i, y	Equation (8)
Where:		
$C_{DW,y}$	 Carbon stock in dead wood within the project boundary point of time in yeary; t EIP 	/ at a given
$C_{DW,i,y}$	 Carbon stock in dead wood in stratum i at a given poin yeary; t EIP 	t of time in
i	= 1, 2, 3, biomass estimation strata within the project	boundary
у	= 1, 2, 3, years elapsed since the start of the ZERO2NA project activity	TURE-PREFOR

6.2. Conservative default-factor based method for estimation of carbon stock in dead wood

33. If PPs do not wish to make sampling based measurements for estimation of C stock in dead wood, they may use the default-factor based method described in this section. The default-factor based method is applicable only if dead wood remains in situ and is not removed from the project boundary through any type of anthropic activities.

34. For all strata to which the default-factor based method is applied, the carbon stock in dead wood is estimated as:

$C_{DW,i,y} = C_{TREE,i,y}$	$_{y} \times 1$	DF_{DW} Equation (9)
Where:		
$C_{DW,i,y}$	=	Carbon stock in dead wood in stratum i at a given point of time in year \mathbf{y} ; t EIP
$C_{TREE,i,y}$	=	Carbon stock in trees biomass in stratum <i>i</i> at a point of time in yeary, as calculated in the tool "Estimation of carbon stocks and change in carbon stocks of trees and shrubs in ZERO2NATURE-PREFOR project activities"; t EIP
DF_{DW}	=	Conservative default factor expressing carbon stock in dead wood as a percentage of carbon stock in tree biomass; per cent
i	=	1, 2, 3, \dots biomass estimation strata within the project boundary
y	=	1, 2, 3, \dots years elapsed since the start of the <code>zero2NATURE-PREFOR</code> project activity



Version I.0 – Scope I7

Value of the conservative default factor expressing carbon stock in dead wood as a percentage of carbon stock in tree biomass (DF_{DW}) is selected according to the guidance provided in the relevant table in Section 8 unless transparent and verifiable information can be provided to justify a different value.

6.3. Change in carbon stock in dead wood

The rate of change of dead wood biomass over a period of time is calculated assuming a linear change. Therefore, the rate of change in carbon stock in dead wood over a period of time is calculated as:

$$dC_{DW,(y_1,y_2)} = \frac{C_{DW,y_2} - C_{DW,y_1}}{T}$$
 Equation (10)

Where:

 $d\mathcal{C}_{DW,(y_1,y_2)}$ = Rate of change in carbon stock in dead wood within the project boundary during the period between a point of time in year y_1 and

a point of time in year y2; t EIP yr-1

 C_{DW,y_2} = Carbon stock in dead wood within the project boundary at a point

of time in year y2; t EIP

 C_{DW,y_1} = Carbon stock in dead wood within the project boundary at a point

of time in year y1; t EIP

T = Time elapsed between two successive estimations $(T=y_2-y_1)$; yr

Change in carbon stock in dead wood within the project boundary in year $y(y_1 \le y \le y_2)$ is given by:

$$\Delta C_{DW,y} = dC_{DW,(y_1,y_2)} \times 1 year \text{ for } y_1 \le y \le y_2$$
 Equation (11)

Where:

 $\Delta C_{DW,y}$ = Change in carbon stock in dead wood within the project boundary

in yeary; t EIP

 $dC_{DW,(y_1,y_2)}$ = Rate of change in carbon stock in dead wood within the project boundary during the period between a point of time in year y_1 and

a point of time in yeary 2; t EIP yr-1

7. ESTIMATION OF CARBON STOCK AND CHANGE IN CARBON STOCK IN WASTE



Version 1.0 – Scope 17

Carbon stock in waste is estimated on the basis of the same strata, and the same sample plots, which are used for the purpose of estimation of living tree biomass. However, PPs applying this tool may use a different stratification for the purpose of estimation of carbon stock in waste if transparent and verifiable information can be given for justification of such a choice.

Two methods are offered for estimation of carbon stock in waste: a measurement-based method and a conservative default-based approach.

7.I. Measurement-based method for estimation of carbon stock in waste

For estimating carbon stock in waste, four waste samples are collected from each sample plot, using a sampling frame which is placed in four randomly selected positions within the plot. The four samples are well mixed into one composite sample and its wet weight is taken. A sub-sample taken from the composite sample is weighed, oven dried, and weighed again to determine its dry weight. The dry-to-wet weight ratio of the sub-sample is calculated and used for estimating the dry weight of the composite waste sample.

Carbon stock in waste biomass in plot *p* is then calculated as:

$C_{W,p,i,y} = \frac{44}{12} \times CF_{W}$	$a_{p,i} \times 2.5 * \frac{A_{p,i}}{a_{p,i}} \times B_{W_WET,p,i} \times DWR_{W,p,i}$	Equation (12)
	W	
Where:		
$C_{W,p,i,y}$	 Carbon stock in litter in plot p in stratum i in yeary; 	t EIP
CF_W	 Carbon fraction of dry biomass in waste; dimension default value of 0.37 is used) 	lless (IPCC
$B_{W_WET,p,i}$	 Wet weight of the composite waste sample collected stratum i; kg 	I from plot p of
$DWR_{W,p,i}$	 Dry-to-wet weight ratio of the waste sub-sample coll plot p in stratum i; dimensionless 	ected from
	Note: it is acceptable to determine this ratio for three selected sample plots in a stratum and then apply the ratio to all plots in that stratum	•
$A_{p,i}$	Area of sample plot <i>p</i> of stratum <i>i</i> ; ha	
$a_{p,i}$	Area of sampling frame for plot p in stratum i ; m^2	
	Note: The numerical factor 2.5 appears in this equal coversion of units from kg to $tonne$ and from m^2 to h because of the fact that $B_{W_WET,p,i}$ is the wet weight collected from an area equal to four times the area of frame	a, as well as of waste
i =	1, 2, 3, biomass estimation strata within the proje	ect boundary
p	1, 2, 3, sample plots in stratum i	
у =	1, 2, 3, years elapsed since the start of the ZERO2 project activity	NATURE-PREFOR



Version I.0 – Scope 17

Carbon stock in waste in stratum i is then calculated as:

$$C_{W,i,y} = \frac{A_i}{A_{PLOT,i}} \sum_{p} C_{W,p,i,y}$$
 Equation (13)

Where:

 $C_{W,i,y}$ = Carbon stock in waste in stratum *i* at a given point of time in year *y*;

 A_i = Area of stratum i; ha

 $A_{PLOT.i}$ = Area of sample plots in stratum i; ha

 $C_{W,p,i,y}$ = Carbon stock inwaste in plot p in stratum i; t EIP

p = 1, 2, 3, ... sample plots in stratum i

i = 1, 2, 3, ... biomass estimation strata within the project boundary

y = 1, 2, 3, ... years elapsed since the start of the ZERO2NATURE-PREFOR project activity

Finally, the carabon stock in waste biomass within the project boundary at a given point of time in year y is calculated by summing up $(C_{W,i,y})$ over all the strata, that is:

$$C_{W,y} = \sum_{i} C_{W,i,y}$$
 Equation (14)

Where:

C_{W,y} = Carbon stock in waste within the project boundary at a given point of time in year y; t EIP

 C_{will} = Carbon stock in waste in stratum i at a given point of time in year y;

i t EIP *i* = 1, 2, 3, ... biomass estimation strata within the project boundary

y = 1, 2, 3, ... years elapsed since the start of the ZERO2NATURE-PREFOR project activity

7.2. Conservative default-factor based method for estimation of carbon stock in waste

If PPs do not wish to make sampling based measurements for estimation of C stock in waste, they may use the default-factor based method described in this section. The default-factor based method



Version I.0 – Scope 17

is applicable only if waste remains in situ and is not removed from the project boundary through any type of anthropic activities.

45. For all strata to which this default method is applied, the carbon stock in waste is estimated as:

$C_{W,i,y} = C_{TREE,i,y}$	$\times DF_{W}$	Equation (15)
Where:		
$C_{W,i,y}$	= Carbon stock in waste in stratum i at a given point of t t EIP	time in year <i>y</i> ;
$C_{TREE,i,y}$	Carbon stock in trees biomass in stratum i at a point of yeary, as calculated in the tool "Estimation of carbon stocks of trees and shrubs in ZER02 PREFOR project activities"; t EIP	stocks and
DF_{LI}	 Conservative default factor expressing carbon stock in percentage of carbon stock in tree biomass; percent 	n waste as a
i	= 1, 2, 3, biomass estimation strata within the project	t boundary
у	= 1, 2, 3, years elapsed since the start of the ZERO2N project activity	ATURE-PREFOR

Value of the conservative default factor expressing carbon stock in waste as a percentage of carbon stock in tree biomass (is selected according to the guidance provided in the relevant table in Section 8 unless transparent and verifiable information can be provided to justify a different value.

7.3. Change in carbon stock in waste

47. The rate of change of waste biomass over a period of time is calculated assuming a linear change. Therefore, the rate of change in carbon stock in waste over a period of time is calculated as:



Version I.0 – Scope 17

$$dC_{W,(y_1,y_2)} = \frac{C_{W,y_2} - C_{W,y_1}}{T}$$
 Equation (16)

Where:

 $dC_{W,(y_1,y_2)}$ = Rate of change in carbon stock in waste within the project boundary

during the period between a point of time in yeary, and a point of time in yeary 2; t EIP yr-1

_ Carbon stock in waste within the project boundary at a point $C_{W,y}$

of time in year y2; t EIP Carbon stock in waste within the project boundary at a point C_{W,y_1}

of time in year y1: t EIP

T = Time elapsed between two successive estimations $(T=y_2-y_1)$; yr

Change in carbon stock in waste within the project boundary in year $y(y_1 \le y \le y_2)$ is given by:

$$\Delta C_{W,y} = dC_{W,(y_1,y_2)} \times 1year \text{ for } y_1 \le y \le y_2$$
 Equation (17)

Where:

 Change in carbon stock in waste within the project boundary $\Delta C_{W,v}$

in yeary; t EIP

= Rate of change in carbon stock in waste within the project $dC_{W,(y_1,y_2)}$

boundary during the period between a point of time in year y1 and

a point of time in yeary 2; t EIP yr-1

8. DATA AND PARAMETERS USED IN THE TOOL

The following tables describe the data and parameters used in this tool. The guidelines contained in these tables regarding selection of data sources, and procedures to be followed in measurement, where applicable, should be treated as an integral part of this tool.



Version I.0 – Scope 17

8.I. Data and parameters not measured

Data / Parameter table 1.

Data / Parameter:	BEF _{2,j}
Data unit:	Dimensionless
Used in equations:	1
Description:	Biomass expansion factor for conversion of stem biomass to above- ground biomass for tree species j
Source of data:	Values from Table 3A.1.10 of IPCC GPG-LULUCF 2003 are used unless transparent and verifiable information can be provided to justify different values
Measurement procedures (if any):	-
Any comment:	BEFs in IPCC literature and national inventory are usually applicable to closed canopy forest. If applied to individual trees growing in an open field it is recommended that the selected BEF be increased by 30 per cent

Data / Parameter:	CF _{TREE}
Data unit:	t C t ⁻¹ d.m.
Used in equations:	3, 5, 6
Description:	Carbon fraction of tree biomass
Source of data:	A value of 0.5 shall be used unless transparent and verifiable information can be provided to justify a different value
Measurement procedures (if any):	-
Any comment:	-



Version I.0 – Scope 17

Data / Parameter table 3.

Data / Parameter:	CF _{LI}
Data unit:	t C t ⁻¹ d.m.
Used in equations:	12
Description:	Carbon fraction of litter biomass
Source of data:	IPCC default value of 0.37 t C t ⁻¹ d.m. may be used
Measurement procedures (if any):	-
Any comment:	-

Data / Parameter table 4.

Data / Parameter:	D _J
Data unit:	t d.m. m ⁻³
Used in equations:	1, 5, 6
Description:	Basic wood density for species j
Source of data:	Values from Table 3A.1.9 of IPCC GPG-LULUCF 2003 are used unless transparent and verifiable information can be provided to justify different values
Measurement procedures (if any):	-
Any comment:	-



Version I.0 – Scope 17

Data / Parameter table 5.

Data / Parameter:	DF _{DW}			
Data unit:	Per cent			
Used in equations:	9	9		
Description:	Conservative default factor expressing carbon stock in dead wood as a percentage of carbon stock in tree biomass			
Source of data:	Defaults conservatively derived from Delaney et al. 1997, Smith et al. 2006, Glenday 2008, Keller et al. 2004, Eaton and Lawrence 2006, Krankina and Harmon 1995, and Clark et al 2002:			
	Biome	Elevation	Precipitation	DF _{DW}
	Tropical	<2000m	<1000 mm yr ⁻¹	2%
	Tropical	<2000m	1000-1600 mm yr ⁻¹	1%
	Tropical	<2000m	>1600 mm yr ⁻¹	6%
	Tropical	>2000m	All	7%
	Temperate/ boreal	All	All	8%
Measurement procedures (if any):	-			
Any comment:	-			



Version I.0 – Scope 17

Data / Parameter table 6.

Data / Parameter:	DF _{LI}	DF _{LI}		
Data unit:	Per cent	Per cent		
Used in equations:	15			
Description:		Default factor for the relationship between carbon stock in litter and carbon stock in living trees		
Source of data:	Defaults conserv	Defaults conservatively derived from sources cited above:		
	Biome	Elevation	Precipitation	$\mathbf{DF_{LI}}$
	Tropical	<2000m	<1000 mm yr ⁻¹	4%
	Tropical	<2000m	1000-1600 mm yr ⁻¹	1%
	Tropical	<2000m	>1600 mm yr ⁻¹	1%
	Tropical	>2000m	All	1%
	Temperate/ boreal	All	All	4%
Measurement procedures (if any):	-			
Any comment:	-			

Data / Parameter table 7.

Data / Parameter:	R _J
Data unit:	Dimensionless
Used in equations:	1, 2, 5
Description:	Root-shoot ratio for species j
Source of data:	The value of R_j shall be calculated as: $R = exp[-1.085+0.9256xln(A)]/A$, where A is above-ground biomass (t d.m. ha ⁻¹) [Source: Table 4.A.4 of IPCC GPG-LULUCF 2003] unless transparent and verifiable information can be provided to justify a different value
Measurement procedures (if any):	-
Any comment:	-



Version I.0 – Scope 17

8.2. Data and parameters measured

Data / Parameter table 8.

Data / Parameter:	A_i
Data unit:	ha
Used in equations:	7, 13
Description:	Area of stratum i
Source of data:	Field measurement
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-

Data / Parameter table 9.

Data / Parameter:	$\mathbf{A}_{\mathtt{PLOT},i}$
Data unit:	ha
Used in equations:	7, 12, 13
Description:	Total area of sample plots in stratum i
Source of data:	Field measurement
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-



Version I.0 – Scope 17

Data / Parameter table 10.

Data / Parameter:	$a_{p,i}$
Data unit:	m ²
Used in equations:	12
Description:	Area of litter sampling frame used in plot p in stratum i
Source of data:	Measurement
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	Often a litter sampling frame of 0.50 m ² is used

Data / Parameter table 11.

Data / Parameter:	$\mathbf{B}_{LI_{LWET},p,i}$
Data unit:	Kg
Used in equations:	12
Description:	Wet weight of the composite litter sample collected from plot p of stratum i ; kg
Source of data:	Field measurements in sample plots
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-



Version I.0 – Scope 17

Data / Parameter table 12.

Data / Parameter:	рвн
Data unit:	cm or any unit of length as specified
Used in equations:	1, 2, 4
Description:	Diameter at breast height of a tree. For the purpose of equations (1) and (2), <i>DBH</i> could be any other diameter or dimensional measurement (e.g. basal diameter, root-collar diameter, basal area, etc.) applicable for the model or data source used
Source of data:	Field measurements in sample plots
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-

Data / Parameter table 13.

Data / Parameter:	\mathbf{D}_n
Data unit:	cm
Used in equations:	6
Description:	Diameter of the n^{th} piece of lying dead wood intersecting a transect line
Source of data:	Field measurements along transect lines in sample plots
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-



Version I.0 – Scope 17

Data / Parameter table 14.

Data / Parameter:	н
Data unit:	m or any other unit of length as specified
Used in equations:	1, 2, 4, 5
Description:	Height of tree
Source of data:	Field measurements in sample plots
Measurement procedures (if any):	Standard operating procedures (SOPs) prescribed under national forest inventory are applied. In the absence of these, SOPs from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Monitoring frequency:	Every five years since the year of the initial verification
QA/QC procedures:	Quality control/quality assurance (QA/QC) procedures prescribed under national forest inventory are applied. In the absence of these, QA/QC procedures from published handbooks, or from the IPCC GPG LULUCF 2003, may be applied
Any comment:	-

Data / Parameter table 15.

Data / Parameter:	Т
Data unit:	Year
Used in equations:	10, 16
Description:	Time period elapsed between two successive estimations of carbon stock
Source of data:	Recorded time
Measurement procedures (if any):	N/A
Monitoring frequency:	-
QA/QC procedures:	-
Any comment:	If the two successive estimations of carbon stock are carried out at different points of time in year y_2 and y_1 , (e.g. in the month of April in year y_1 and in the month of September in year y_2), then a fractional value shall be assigned to T

	Document information	
Version	Date	Description
1.0	September 24, 2012	Tool